

Enclosure C

[Home](#) | [Xbox Games](#) | [PC Games](#)[Combat Flight Simulator 2](#)[Everyone](#)[System Requirements](#)[Buy It](#)[Register](#)[Support](#)[Bookmark Page](#)[Send to a Friend](#)[Print](#)

## Setting and Changing Aircraft Parameters

**Software Developer Kit #1**

[11.29.00]

In Combat Flight Simulator 2, as in Microsoft Flight Simulator 98 and 2000, you can import new aircraft and add or change values in the associated aircraft.cfg file to modify aircraft behavior, performance, and damage.

### A B O U

This is the first in a series of articles for Microsoft® Flight Simulator 2.

**IMPORTANT:** The information included in the SDK is intended as a reference for programmers. It assumes familiarity with C programming language, Macro Assembler (MASM), and game development. The information is not supported by Microsoft Product Support.

This document shows how to set several aircraft parameters that have been added since the introduction of Flight Simulator 2000.

Specifically, it shows:

- How the aircraft responds to contact with the ground or ground objects
- How to simulate flap articulation
- How the door or cockpit egress works
- How the wings fold (on carrier-based aircraft)
- How the arresting gear affects the aircraft (on carrier-based aircraft)
- How to modify the pilot's view or eyepoint
- How to alter the speed at which the Landing Signals Officer (LSO) lights lead in to land

In this article we explore the mechanical aspects of changing aircraft performance.

In future articles we will discuss:

- Converting CFS1 aircraft files
- Importing additional aircraft
- Adding or changing terrain
- Building missions and campaigns

For a general discussion of the aircraft.cfg and all its uses, go to the Flight SDK, scroll down and then download the **Aircraft Container** section.

### Reaction to Contact

In Microsoft Combat Flight Simulator 2 you can configure and adjust the vehicle's reaction to different kinds of contact, including landing gear contact and articulation.

You can also configure each contact point independently for each aircraft limit to the number of points you can add. The data for configuring the p in the [contact\_points] section of the *aircraft.cfg*. When importing that does not contain this set of data, the program will generate the data the first time the aircraft is loaded, and then write it to the *aircraft.cfg*.

Each contact point contains a series of values that define the characteristic separated by commas. Each point's data set takes the form point.n= where to the particular point, followed by the data.

```
[contact_points]
point.0= 1, -18.00, 0.00, -3.35, 3200.0, 0, 0.
0.25, 2.5, 0.90, 1.0, 4.00, 0, 0, 200
```

### Elements:

- 6/14/2006

- 6=Right Wing, 7=Aux1 Scrape, 8=Aux2 Scrape, 9=Tail Scrape
- **Airspeed Limit:** The speed at which extension becomes inhibited, in (zero) to ignore this functionality. This is a function of the Realism this number for non-retractable gear.
- **Damage from airspeed:** The speed above which gear accrues damage; effect is scaled by the Realism settings. Omit it for non-retractable

#### Other contact reaction parameters:

- **max\_number\_of\_points:** The maximum number of points that the p for in the [contact\_reaction] section. The default is 25 if you do not
- **static\_cg\_height , static\_pitch:** The height and pitch of the aircraft the surface. The program uses these values when placing the aircraft at startup, when slewing, and any other time the simulation is not aircraft position.

#### Flap Articulation

You can configure wing flap articulation in the [Flaps . 0] section of the

You can specify the normal flap extension/retraction time in seconds with parameter:

Extending-time=time

Position 0 (zero) should always refer to the fully retracted position, and the positions should be in the corresponding order from fully retracted to full

following list of parameters defines the characteristics of each flap position

```
Flaps-position.0=0, 0
Flaps-position.1=45, 200
Flaps-position.2=90, 100
```

The .n (.0, .1, and .2 above) indexes the discrete position available in the The first parameter is the extension in degrees. The second parameter is airspeed, in knots, above which flap movement may be inhibited. A value this parameter specifies no limit.

Flaps can be damaged (scaled by Realism) if flown above the indicated air by using:

Damaging-speed = speed

Slow or inhibited movement may evidence this damage. Flaps may be seen even departing the aircraft, if the speed exceeds that specified in:

Blowout-speed = speed

#### Aircraft Exits

You can specify the characteristics of the aircraft's main door as follows:

```
[exits]
number_of_exits = 1
exit_rate.0 = 0.4
```

where exit\_rate is the percent per second, or simply 1/time to open

#### Folding Wings

You can specify the folding wing characteristics of carrier-based aircraft :

```
[folding_wings]
wing_fold_system_type = 1
fold_rates = 0.12,0.11
```

You can set `wing_fold_system_type` to 1 or 0. "1" specifies that wings are foldable; "0" means the wings can't fold. The first `fold_rate` specifies the left wing rate, and the second specifies the right wing rate. indicates *percent per second*.

### Arresting Gear

You can configure arresting gear on carrier-based aircraft as follows:

```
[TailHook]
tailhook_length=4
tailhook_position = -15.0, 0.0, -1.0
cable_force_adjust = 1.0
```

where the `tailhook_length` is in feet from the `tailhook_pos` the position, in feet, from the datum point of the aircraft. You can use it to increase or decrease the tension to which the cables are adjusted for tailhook cable tension is automatically configured for this aircraft's mass and normal speeds, so this term is usually correct at the default value of 1.0.

### Views

You can specify the pilot's normal eyepoint (the position of his eyes relative to the aircraft and therefore his view) as follows:

```
[Views]
eyepoint= -6.2, 0.00, 3.55
```

These values represent the longitudinal, lateral, and vertical positions, in feet, from the normal eye position.

### Landing Signal Officer

In CFS2 the speed at which the LSO brings an aircraft in to land on the carrier is based on characteristics specific to that aircraft. Specifically, to determine the landing speed, CFS2 uses the following formula:

"LSO speed" \* stall speed \* 1.45 = descent velocity

You can scale landing speed using the following parameter:

```
[LSO]
LSOAdjustSpeed = 1.0
```

To increase the aircraft landing speed, increase the value for "LSOAdjustSpeed" in increments of 0.1 (1, 1.1, 1.2, etc.).

### Propeller Rotation

New to CFS version 2 is the ability to adjust the rotation of each player-flight propeller. You can adjust this function by manipulating the "rotation" value in the `[propeller]` section of the *aircraft.cfg*

(see the "Aircraft Container" section of the [FS2000 SDK](#) for details).

Below is an example of the new rotation functionality from the P-38 *aircraft*

```
[propeller]  
thrust_scalar=1.0  
rotation= -1,1
```

The thrust generated by a given propeller is a function of the power delivered to the propeller shaft, RPM, blade angle, airplane speed, and ambient density. The `thrust_scalar` parameter scales the calculated thrust for propeller engines.

Note that the rotation values are comma separated, and are in engine number order. The value "-1" describes the rotation as counter-clockwise (as viewed by the pilot) of the (left) engine.

---

© 2000 Microsoft Corporation and/or its suppliers. All rights reserved.